




## 02 - OMLEX - Network Boot - BIOS Setting

This guide is describing how to setup OMLEX computer BIOS in order to boot from the network

Written By: Petr Roupec




## Step 1 — Enter OMLEX Computer BIOS





- Enter into BIOS by pressing DEL key right after computer start

## Step 2 — Enter OMLEX Computer BIOS



- To enter BIOS pres DEL Key right after computer start
- By pressing left arrow go to the Boot Section
- Enter boot setting configuration


### Step 3 — Enable LAN Booting



- Scroll down and enable Boot from LAN


**⚠ Save Changes and Reboot computer is required prior changing boot priority devices**

### Step 4 — Reboot computer




- Save changes and leave BIOS

## Step 5 — Enter into BIOS and Change Booting order



- To enter BIOS pres DEL Key right after computer start
- Change booting priority

## Step 6



- Save changes and leave BIOS